G01EDF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

G01EDF returns the probability for the lower or upper tail of the F or variance-ratio distribution with real degrees of freedom, via the routine name.

2 Specification

real FUNCTION GO1EDF(TAIL, F, DF1, DF2, IFAIL)

INTEGER IFAIL

real F, DF1, DF2

CHARACTER*1 TAIL

3 Description

The lower tail probability for the F, or variance-ratio distribution, with ν_1 and ν_2 degrees of freedom, $P(F \leq f : \nu_1, \nu_2)$, is defined by:

$$P(F \leq f: \nu_1, \nu_2) = \frac{\nu_1^{\nu_1/2} \nu_2^{\nu_2/2} \Gamma\left((\nu_1 + \nu_2)/2\right)}{\Gamma(\nu_1/2) \Gamma(\nu_2/2)} \int_0^f F^{(\nu_1 - 2)/2} (\nu_1 F + \nu_2)^{-(\nu_1 + \nu_2)/2} dF,$$

for $\nu_1, \, \nu_2 > 0, \, f \ge 0$.

The probability is computed by means of a transformation to a beta distribution, $P_{\beta}(B \leq \beta : a, b)$:

$$P(F \le f : \nu_1, \nu_2) = P_{\beta} \left(B \le \frac{\nu_1 f}{\nu_1 f + \nu_2} : \nu_1 / 2, \nu_2 / 2 \right)$$

and using a call to G01EEF.

For very large values of both ν_1 and ν_2 , greater than 10^5 , a normal approximation is used. If only one of ν_1 or ν_2 is greater than 10^5 then a χ^2 approximation is used, see Abramowitz and Stegun [1].

4 References

- [1] Abramowitz M and Stegun I A (1972) Handbook of Mathematical Functions Dover Publications (3rd Edition)
- [2] Hastings N A J and Peacock J B (1975) Statistical Distributions Butterworths

5 Parameters

1: TAIL — CHARACTER*1

Input

On entry: indicates whether an upper or lower tail probability is required.

If TAIL = 'L', then the lower tail probability is returned, i.e., $P(F \le f : \nu_1, \nu_2)$.

If TAIL = 'U', then the upper tail probability is returned, i.e., $P(F \ge f : \nu_1, \nu_2)$.

Constraint: TAIL = 'L' or 'U'.

2: F-real

On entry: the value of the F variate, f.

Constraint: $F \geq 0$.

[NP3390/19/pdf] G01EDF.1

3: DF1-real Input

On entry: the degrees of freedom of the numerator variance, ν_1 .

Constraint: DF1 > 0.0.

4: DF2 - real Input

On entry: the degrees of freedom of the denominator variance, ν_2 .

Constraint: DF2 > 0.0.

5: IFAIL — INTEGER Input/Output

On entry: IFAIL must be set to 0, -1 or 1. Users who are unfamiliar with this parameter should refer to Chapter P01 for details.

On exit: IFAIL = 0 unless the routine detects an error or gives a warning (see Section 6).

For this routine, because the values of output parameters may be useful even if IFAIL $\neq 0$ on exit, users are recommended to set IFAIL to -1 before entry. It is then essential to test the value of IFAIL on exit.

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings specified by the routine:

If IFAIL = 1, 2 or 3 on exit, then G01EDF returns 0.0.

IFAIL = 1

On entry, $TAIL \neq L'$ or 'U'.

IFAIL = 2

On entry, F < 0.0.

IFAIL = 3

On entry, DF1 \leq 0.0, or DF2 \leq 0.0.

IFAIL = 4

F is too far out into the tails for the probability to be evaluated exactly. The result tends to approach 1.0 if x is large, or 0.0 if x is small. The result returned is a good approximation to the required solution.

7 Accuracy

The result should be accurate to 5 significant digits.

8 Further Comments

For higher accuracy G01EEF can be used along with the transformations given in Section 3.

9 Example

Values from, and degrees of freedom for F-distributions are read, the lower-tail probabilities computed, and all these values printed, until the end of data is reached.

G01EDF.2 [NP3390/19/pdf]

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
GO1EDF Example Program Text
     Mark 14 Release. NAG Copyright 1989.
      .. Parameters ..
      INTEGER
                      NIN, NOUT
     PARAMETER
                      (NIN=5, NOUT=6)
      .. Local Scalars ..
                      DF1, DF2, F, PROB
     real
      INTEGER
                       IFAIL
      .. External Functions ..
     real
                       G01EDF
     EXTERNAL
                       G01EDF
      .. Executable Statements ..
     WRITE (NOUT,*) 'GO1EDF Example Program Results'
     Skip heading in data file
     READ (NIN,*)
     WRITE (NOUT,*)
     WRITE (NOUT,*) '
                                DF1
                                        DF2
                                               PROB'
                         F
     WRITE (NOUT,*)
  20 READ (NIN, *, END=40) F, DF1, DF2
      IFAIL = -1
     PROB = GO1EDF('Lower',F,DF1,DF2,IFAIL)
     IF (IFAIL.EQ.O) THEN
        WRITE (NOUT,99999) F, DF1, DF2, PROB
     ELSE
        WRITE (NOUT, 99999) F, DF1, DF2, PROB, 'NOTE: IFAIL = ', IFAIL
     END IF
      GO TO 20
  40 STOP
99999 FORMAT (1X,F6.3,2F8.3,F8.4,A,I1)
     END
```

9.2 Program Data

```
G01EDF Example Program Data
5.5 1.5 25.5
39.9 1.0 1.0
2.5 20.25 1.0
```

9.3 Program Results

GO1EDF Example Program Results

```
F DF1 DF2 PR0B

5.500 1.500 25.500 0.9837
39.900 1.000 1.000 0.9000
2.500 20.250 1.000 0.5342
```

[NP3390/19/pdf] G01EDF.3 (last)