#### S09ABF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

## 1 Purpose

S09ABF returns the value of the inverse circular cosine,  $\arccos x$ , via the routine name; the result is in the principal range  $(0, \pi)$ .

## 2 Specification

real FUNCTION SO9ABF(X, IFAIL) INTEGER IFAIL real X

## 3 Description

The routine calculates an approximate value for the inverse circular cosine,  $\arccos x$ . It is based on the Chebyshev expansion

$$\arcsin x = x \times y(t) = x \sum_{r=0}^{\prime} a_r T_r(t)$$

where  $\frac{-1}{\sqrt{2}} \le x \le \frac{1}{\sqrt{2}}$ , and  $t = 4x^2 - 1$ .

For  $x^2 \le \frac{1}{2}$ ,  $\arccos x = \frac{\pi}{2} - \arcsin x$ .

For 
$$-1 \le x < \frac{-1}{\sqrt{2}}$$
,  $\arccos x = \pi - \arcsin \sqrt{1 - x^2}$ .

For 
$$\frac{1}{\sqrt{2}} < x \le 1$$
,  $\arccos x = \arcsin \sqrt{1 - x^2}$ .

For |x| > 1,  $\arccos x$  is undefined and the routine fails.

### 4 References

[1] Abramowitz M and Stegun I A (1972) Handbook of Mathematical Functions Dover Publications (3rd Edition)

#### 5 Parameters

1: X - real

On entry: the argument x of the function.

Constraint:  $|X| \le 1.0$ .

2: IFAIL — INTEGER Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

# 6 Error Indicators and Warnings

Errors detected by the routine:

IFAIL = 1

S09ABF has been called with |X| > 1.0, for which arccos is undefined. A zero result is returned.

[NP3390/19/pdf] S09ABF.1

### 7 Accuracy

If  $\delta$  and  $\epsilon$  are the relative errors in the argument and the result, respectively, then in principle

$$|\epsilon| \simeq \left| \frac{x}{\arccos x \sqrt{1 - x^2}} \times \delta \right|.$$


The equality should hold if  $\delta$  is greater than the **machine precision** ( $\delta$  is due to data errors etc.), but if  $\delta$  is due simply to round-off in the machine it is possible that rounding etc. in internal calculations may lose one extra figure.

The behaviour of the amplification factor  $\frac{x}{\arccos x\sqrt{1-x^2}}$  is shown in the graph below.

In the region of x=0 this factor tends to zero and the accuracy will be limited by the **machine precision**. For |x| close to one,  $1-|x|\sim\delta$ , the above analysis is not applicable owing to the fact that both the argument and the result are bounded  $|x|\leq 1$ ,  $0\leq \arccos x\leq \pi$ .

In the region of  $x \sim -1$  we have  $\epsilon \sim \sqrt{\delta}$ , that is the result will have approximately half as many correct significant figures as the argument.

In the region  $x \sim +1$ , we have that the absolute error in the result, E, is given by  $E \sim \sqrt{\delta}$ , that is the result will have approximately half as many decimal places correct as there are correct figures in the argument.



### 8 Further Comments

None.

# 9 Example

The following program reads values of the argument x from a file, evaluates the function at each value of x and prints the results.

S09ABF.2 [NP3390/19/pdf]

#### 9.1 Program Text

**Note.** The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
S09ABF Example Program Text
     Mark 14 Revised. NAG Copyright 1989.
      .. Parameters ..
      INTEGER
                      NIN, NOUT
     PARAMETER
                      (NIN=5,NOUT=6)
      .. Local Scalars ..
                       X, Y
     real
      INTEGER
      .. External Functions ..
                       S09ABF
     real
     EXTERNAL
                       S09ABF
      .. Executable Statements ..
     WRITE (NOUT,*) 'S09ABF Example Program Results'
     Skip heading in data file
     READ (NIN,*)
     WRITE (NOUT,*)
     WRITE (NOUT,*) '
                           X
                                       Y
                                                IFAIL'
     WRITE (NOUT,*)
   20 READ (NIN, *, END=40) X
     IFAIL = 1
     Y = SO9ABF(X,IFAIL)
     WRITE (NOUT,99999) X, Y, IFAIL
     GO TO 20
   40 STOP
99999 FORMAT (1X,1P,2e12.3,17)
     END
```

#### 9.2 Program Data

```
SO9ABF Example Program Data

-0.5

0.1

0.9

2.0

-1.5
```

### 9.3 Program Results

SO9ABF Example Program Results

Х	Y	IFAIL
-5.000E-01	2.094E+00	0
1.000E-01	1.471E+00	0
9.000E-01	4.510E-01	0
2.000E+00	0.000E+00	1
-1.500E+00	0.000E+00	1

[NP3390/19/pdf] S09ABF.3 (last)