M01DFF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

M01DFF ranks the rows of a matrix of integer numbers in ascending or descending order.

2 Specification

SUBROUTINE MO1DFF(IM, LDM, M1, M2, N1, N2, ORDER, IRANK, IFAIL)

INTEGER IM(LDM,N2), LDM, M1, M2, N1, N2, IRANK(M2), IFAIL

CHARACTER*1 ORDER

3 Description

M01DFF ranks rows M1 to M2 of a matrix, using the data in columns N1 to N2 of those rows. The ordering is determined by first ranking the data in column N1, then ranking any tied rows according to the data in column N1 + 1, and so on up to column N2.

M01DFF uses a variant of list-merging, as described by Knuth [1] pp 165-166. The routine takes advantage of natural ordering in the data, and uses a simple list insertion in a preparatory pass to generate ordered lists of length at least 10. The ranking is stable: equal rows preserve their ordering in the input data.

4 References

[1] Knuth D E (1973) The Art of Computer Programming (Volume 3) Addison-Wesley (2nd Edition)

5 Parameters

1: IM(LDM,N2) — INTEGER array

Inpu

On entry: columns N1 to N2 of rows M1 to M2 of IM must contain INTEGER data to be ranked.

2: LDM — INTEGER

Innut

On entry: the first dimension of the array IM as declared in the (sub)program from which M01DFF is called.

Constraint: LDM > M2.

3: M1 — INTEGER

Input

On entry: the index of the first row of IM to be ranked.

Constraint: M1 > 0.

4: M2 — INTEGER

Input

On entry: the index of the last row of IM to be ranked.

Constraint: $M2 \ge M1$.

5: N1 — INTEGER

Input

On entry: the index of the first column of IM to be used.

Constraint: N1 > 0.

[NP3390/19/pdf] M01DFF.1

M01 – Sorting

6: N2 — INTEGER

On entry: the index of the last column of IM to be used.

Constraint: $N2 \ge N1$.

7: ORDER — CHARACTER*1

Input

On entry: if ORDER is 'A', the rows will be ranked in ascending (i.e., non-decreasing) order; if ORDER is 'D', into descending order.

Constraint: ORDER = 'A' or 'D'.

8: IRANK(M2) — INTEGER array

Output

On exit: elements M1 to M2 of IRANK contain the ranks of the corresponding rows of IM. Note that the ranks are in the range M1 to M2: thus, if the ith row of IM is the first in the rank order, IRANK(i) is set to M1.

9: IFAIL — INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors detected by the routine:

IFAIL = 1

On entry, M2 < 1, or N2 < 1, or M1 < 1, or M1 > M2, or N1 < 1, or N1 > N2, or LDM < M2.

IFAIL = 2

On entry, ORDER is not 'A' or 'D'.

7 Accuracy

Not applicable.

8 Further Comments

The average time taken by the routine is approximately proportional to $n \times \log n$, where n = M2 - M1 + 1.

9 Example

The example program reads a matrix of integers and ranks the rows in descending order.

M01DFF.2 [NP3390/19/pdf]

M01-Sorting M01DFF

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
MO1DFF Example Program Text
     Mark 14 Revised. NAG Copyright 1989.
      .. Parameters ..
      INTEGER
                       MMAX, NMAX
     PARAMETER
                       (MMAX=20,NMAX=20)
      INTEGER
                       NIN, NOUT
     PARAMETER
                        (NIN=5, NOUT=6)
      .. Local Scalars ..
     INTEGER
                       I, IFAIL, J, M, N
      .. Local Arrays ..
     INTEGER
                       IM(MMAX,NMAX), IRANK(MMAX)
      .. External Subroutines ..
     EXTERNAL
                       MO1DFF
      .. Executable Statements ..
     WRITE (NOUT,*) 'MO1DFF Example Program Results'
     Skip heading in data file
     READ (NIN,*)
     READ (NIN,*) M, N
      IF (M.GE.1 .AND. M.LE.MMAX .AND. N.GE.1 .AND. N.LE.NMAX) THEN
         DO 20 I = 1, M
            READ (NIN,*) (IM(I,J),J=1,N)
  20
         CONTINUE
         IFAIL = 0
         CALL MO1DFF(IM, MMAX, 1, M, 1, N, 'Descending', IRANK, IFAIL)
         WRITE (NOUT,*)
         WRITE (NOUT,*) 'Data
                                                      Ranks'
         WRITE (NOUT,*)
         DO 40 I = 1, M
            WRITE (NOUT, 99999) (IM(I, J), J=1, N), IRANK(I)
  40
         CONTINUE
     END IF
     STOP
99999 FORMAT (1X,317,111)
     END
```

[NP3390/19/pdf] M01DFF.3

M01DFF M01 - Sorting

9.2 Program Data

MO1DFF Example Program Data

12 3

6 5 4

5 2 1

2 4 9

4 9 6

4 9 5

4 1 2

3 4 1

2 4 6

1 6 4

9 3 2

6 2 5

4 9 6

9.3 Program Results

MO1DFF Example Program Results

Data				Ranks
	6	5	4	2
	5	2	1	4
	2	4	9	10
	4	9	6	5
	4	9	5	7
	4	1	2	8
	3	4	1	9
	2	4	6	11
	1	6	4	12
	9	3	2	1
	6	2	5	3
	4	9	6	6

M01DFF.4 (last) [NP3390/19/pdf]