

## F08NWF (CGEBAK/ZGEBAK) – NAG Fortran Library Routine Document

**Note.** Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

### 1 Purpose

F08NWF (CGEBAK/ZGEBAK) transforms eigenvectors of a balanced matrix to those of the original complex general matrix.

### 2 Specification

```

SUBROUTINE F08NWF(JOB, SIDE, N, ILO, IHI, SCALE, M, V, LDV, INFO)
ENTRY      cgebak(JOB, SIDE, N, ILO, IHI, SCALE, M, V, LDV, INFO)
INTEGER    N, ILO, IHI, M, LDV, INFO
real      SCALE(*)
complex  V(LDV,*)
CHARACTER*1 JOB, SIDE

```

The ENTRY statement enables the routine to be called by its LAPACK name.

### 3 Description

This routine is intended to be used after a complex general matrix  $A$  has been balanced by F08NVF (CGEBAL/ZGEBAL), and eigenvectors of the balanced matrix  $A''_{22}$  have subsequently been computed.

For a description of balancing, see the document for F08NVF. The balanced matrix  $A''$  is obtained as  $A'' = DPAP^T D^{-1}$ , where  $P$  is a permutation matrix and  $D$  is a diagonal scaling matrix. This routine transforms left or right eigenvectors as follows:

- if  $x$  is a right eigenvector of  $A''$ ,  $P^T D^{-1} x$  is a right eigenvector of  $A$ ;
- if  $y$  is a left eigenvector of  $A''$ ,  $P^T D y$  is a left eigenvector of  $A$ ;

### 4 References

None.

### 5 Parameters

- 1:** JOB — CHARACTER\*1 *Input*  
*On entry:* this **must** be the same parameter JOB as supplied to F08NVF (CGEBAL/ZGEBAL).  
*Constraint:* JOB = 'N', 'P', 'S' or 'B'.
- 2:** SIDE — CHARACTER\*1 *Input*  
*On entry:* indicates whether left or right eigenvectors are to be transformed, as follows:  
     if SIDE = 'L', then left eigenvectors are transformed;  
     if SIDE = 'R', then right eigenvectors are transformed.  
*Constraint:* SIDE = 'L' or 'R'.
- 3:** N — INTEGER *Input*  
*On entry:*  $n$ , the number of rows of the matrix of eigenvectors.  
*Constraint:*  $N \geq 0$ .

- 4: ILO — INTEGER *Input*  
 5: IHI — INTEGER *Input*  
*On entry:* the values  $i_{lo}$  and  $i_{hi}$ , as returned by F08NVF (CGEBAL/ZGEBAL).  
*Constraints:*
- $$1 \leq \text{ILO} \leq \text{IHI} \leq N \text{ if } N > 0,$$
- $$\text{ILO} = 1 \text{ and } \text{IHI} = 0 \text{ if } N = 0.$$
- 6: SCALE(\*) — *real* array *Input*  
**Note:** the dimension of the array SCALE must be at least  $\max(1, N)$ .  
*On entry:* details of the permutations and/or the scaling factors used to balance the original complex general matrix, as returned by F08NVF (CGEBAL/ZGEBAL).
- 7: M — INTEGER *Input*  
*On entry:*  $m$ , the number of columns of the matrix of eigenvectors.  
*Constraint:*  $M \geq 0$ .
- 8: V(LDV,\*) — *complex* array *Input/Output*  
**Note:** the second dimension of the array V must be at least  $\max(1, M)$ .  
*On entry:* the matrix of left or right eigenvectors to be transformed.  
*On exit:* the transformed eigenvectors.
- 9: LDV — INTEGER *Input*  
*On entry:* the first dimension of the array V as declared in the (sub)program from which F08NWF (CGEBAK/ZGEBAK) is called.  
*Constraint:*  $\text{LDV} \geq \max(1, N)$ .
- 10: INFO — INTEGER *Output*  
*On exit:*  $\text{INFO} = 0$  unless the routine detects an error (see Section 6).

## 6 Error Indicators and Warnings

INFO < 0

If  $\text{INFO} = -i$ , the  $i$ th parameter had an illegal value. An explanatory message is output, and execution of the program is terminated.

## 7 Accuracy

The errors are negligible.

## 8 Further Comments

The total number of real floating-point operations is approximately proportional to  $nm$ .

The real analogue of this routine is F08NJJF (SGEBAK/DGEBAK).

## 9 Example

See the example for Section 9 of the document for F08NVF.