

D02NTF – NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

D02NTF is a setup routine which must be called by the user, prior to an integrator in the subchapter D02M–D02N, if banded matrix linear algebra is required.

2 Specification

```

SUBROUTINE D02NTF(NEQ, NEQMAX, JCEVAL, ML, MU, NWKJAC, NJCPVT,
1              RWORK, IFAIL)
  INTEGER      NEQ, NEQMAX, ML, MU, NWKJAC, NJCPVT, IFAIL
  real       RWORK(50+4*NEQMAX)
  CHARACTER*1  JCEVAL

```

3 Description

This routine defines the linear algebra to be used as banded matrix linear algebra, permits the user to specify the method for calculating the Jacobian and checks the validity of certain input values.

4 References

None.

5 Parameters

- 1:** NEQ — INTEGER *Input*
On entry: the number of differential equations.
Constraint: $1 \leq \text{NEQ} \leq \text{NEQMAX}$.
- 2:** NEQMAX — INTEGER *Input*
On entry: a bound on the maximum number of differential equations to be solved during the integration.
Constraint: $\text{NEQMAX} \geq \text{NEQ}$.
- 3:** JCEVAL — CHARACTER*1 *Input*
On entry: specifies the technique to be used to compute the Jacobian as follows:
- JCEVAL = 'N'
the Jacobian is to be evaluated numerically by the integrator. If this option is used, then the actual argument corresponding to JAC in the call to D02NCF or D02NHF must be either D02NCZ or D02NHZ respectively.
- JCEVAL = 'A'
the user will supply a subroutine to evaluate the Jacobian on a call to the integrator.
- JCEVAL = 'D'
the default choice is to be made. In this case 'D' is interpreted as 'N'.
- Only the first character of the actual argument JCEVAL is passed to D02NTF; hence it is permissible for the actual argument to be more descriptive e.g., 'Numerical', 'Analytical' or 'Default' on a call to D02NTF.
- Constraint:* JCEVAL = 'N', 'A' or 'D'.

- 4:** ML — INTEGER *Input*
On entry: the number of sub-diagonals in the band, m_L .
Constraint: $0 \leq ML \leq NEQ-1$.
- 5:** MU — INTEGER *Input*
On entry: the number of super-diagonals in the band, m_U .
Constraint: $0 \leq MU \leq NEQ-1$.
- 6:** NWKJAC — INTEGER *Input*
On entry: the size of the workspace array WKJAC, which the user is supplying to the integrator, as declared in the (sub)program from which D02NTF is called.
Constraint: $NWKJAC \geq (2 \times ML + MU + 1) \times NEQMAX$.
- 7:** NJCPVT — INTEGER *Input*
On entry: the size of the workspace array JACPVT, which the user is supplying to the integrator, as declared in the (sub)program from which D02NTF is called.
Constraint: $NJCPVT \geq NEQMAX$.
- 8:** RWORK(50+4*NEQMAX) — *real* array *Workspace*
This must be the same workspace array as the array RWORK supplied to the integrator. It is used to pass information from the setup routine to the integrator and therefore the contents of this array must not be changed before calling the integrator.
- 9:** IFAIL — INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.
On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors detected by the routine:

IFAIL = 1

- On entry, JCEVAL \neq 'N' or 'A' or 'D',
- or $NEQ < 1$,
- or $ML < 0$ or $ML > NEQ - 1$,
- or $MU < 0$ or $MU > NEQ - 1$,
- or $NEQ > NEQMAX$,
- or $NJCPVT < NEQMAX$,
- or $NWKJAC < (2 \times ML + MU + 1) \times NEQMAX$.

7 Accuracy

Not applicable.

8 Further Comments

This routine must be called as a setup routine before a call to either D02NCF or D02NHF and may be called as the linear algebra setup routine before a call to either D02NMF or D02NNF.

9 Example

See the example for Section 9 of the document for D02NCF and Section 9 of the document for D02NHF.
