G02DFF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

G02DFF deletes an independent variable from a general linear regression model.

2 Specification

```
SUBROUTINE GO2DFF(IP, Q, LDQ, INDX, RSS, WK, IFAIL)
INTEGER IP, LDQ, INDX, IFAIL
real Q(LDQ,IP+1), RSS, WK(2*IP)
```

3 Description

When selecting a linear regression model it is sometimes useful to drop independent variables from the model and to examine the resulting sub-model. G02DFF updates the QR decomposition used in the computation of the linear regression model. The QR decomposition may come from G02DAF, G02DEF or a previous call to G02DFF.

For the general linear regression model with p independent variables fitted G02DAF or G02DEF compute a QR decomposition of the (weighted) independent variables and form an upper triangular matrix R and a vector c. To remove an independent variable R and c have to be updated. The column of R corresponding to the variable to be dropped is removed and the matrix is then restored to upper triangular form by applying a series of Givens rotations. The rotations are then applied to c. Note only the first p elements of c are affected.

The method used means that while the updated values of R and c are computed an updated value of Q from the QR decomposition is not available so a call to G02DEF cannot be made after a call to G02DFF.

G02DDF can be used to calculate the parameter estimates, $\hat{\beta}$, from the information provided by G02DFF.

4 References

- [1] Golub G H and van Loan C F (1996) Matrix Computations Johns Hopkins University Press (3rd Edition), Baltimore
- [2] Hammarling S (1985) The singular value decomposition in multivariate statistics SIGNUM Newsl. 20 (3) 2–25

5 Parameters

1: IP — INTEGER

On entry: the number of independent variables already in the model, p.

Constraint: $IP \geq 1$.

2: Q(LDQ,IP+1) - real array

Input/Output

On entry: the results of the QR decomposition as returned by routines G02DAF, G02DCF, G02DEF, G02EEF or previous calls to G02DFF.

On exit: the updated QR decomposition:

3: LDQ — INTEGER

On entry: the first dimension of the array Q as declared in the (sub)program from which G02DFF is called.

Constraint: LDQ > IP.

[NP3390/19/pdf] G02DFF.1

4: INDX — INTEGER Input

On entry: indicates which independent variable is to be deleted from the model.

Constraint: $1 \leq INDX \leq IP$.

5: RSS-real Input/Output

On entry: the residual sum of squares for the full regression.

Constraint: RSS ≥ 0.0 .

On exit: the residual sum of squares with the (INDX)th variable removed. Note the residual sum of squares will only be valid if the regression is of full rank, otherwise the residual sum of squares should be obtained using G02DDF.

6: WK(2*IP) - real array

Work space

7: IFAIL — INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors detected by the routine:

IFAIL = 1

On entry, IP < 1, or LDQ < IP, or INDX < 1, or INDX > IP, or RSS < 0.0.

IFAIL = 2

On entry, a diagonal element of R is zero.

7 Accuracy

There will inevitably be some loss in accuracy in fitting a model by dropping terms from a more complex model rather than fitting it afresh using G02DAF.

8 Further Comments

None.

9 Example

A data set consisting of 12 observations on four independent variables and one dependent variable is read in. The full model, including a mean term, is fitted using G02DAF. The value of INDX is read in and that variable dropped from the regression. The parameter estimates are calculated by G02DDF and printed. This process is repeated until INDX is 0.

G02DFF.2 [NP3390/19/pdf]

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
GO2DFF Example Program Text
   Mark 14 Release. NAG Copyright 1989.
   .. Parameters ..
   INTEGER
                    MMAX, NMAX
   PARAMETER
                     (MMAX=5,NMAX=12)
   INTEGER
                    NIN, NOUT
   PARAMETER
                    (NIN=5, NOUT=6)
   .. Local Scalars ..
                    RSS, TOL
   real
   INTEGER
                    I, IDF, IFAIL, INDX, IP, IRANK, J, M, N
   LOGICAL
                    SVD
                    MEAN, WEIGHT
   CHARACTER
   .. Local Arrays ..
                    B(MMAX), COV((MMAX*MMAX+MMAX)/2), H(NMAX),
   real
                    P(MMAX*(MMAX+2)), Q(NMAX,MMAX+1), RES(NMAX)
                    SE(MMAX), WK(5*(MMAX-1)+MMAX*MMAX), WT(NMAX),
                    X(NMAX, MMAX), Y(NMAX)
   INTEGER
                    ISX (MMAX)
   .. External Subroutines ..
                    GO2DAF, GO2DDF, GO2DFF
   EXTERNAL
   .. Executable Statements ..
   WRITE (NOUT,*) 'GO2DFF Example Program Results'
   Skip heading in data file
   READ (NIN,*)
   READ (NIN,*) N, M, WEIGHT, MEAN
   IF (N.LE.NMAX .AND. M.LT.MMAX) THEN
      IF (WEIGHT.EQ.'W' .OR. WEIGHT.EQ.'w') THEN
         DO 20 I = 1, N
            READ (NIN,*) (X(I,J),J=1,M), Y(I), WT(I)
20
         CONTINUE
      ELSE
         DO 40 I = 1, N
            READ (NIN,*) (X(I,J),J=1,M), Y(I)
40
         CONTINUE
      END IF
      DO 60 I = 1, M
         ISX(I) = 1
60
      CONTINUE
      IP = M
      IF (MEAN.EQ.'M' .OR. MEAN.EQ.'m') IP = IP + 1
      Set tolerance
      TOL = 0.00001e0
      IFAIL = 0
      CALL GO2DAF (MEAN, WEIGHT, N, X, NMAX, M, ISX, IP, Y, WT, RSS, IDF, B, SE,
                  COV, RES, H, Q, NMAX, SVD, IRANK, P, TOL, WK, IFAIL)
      WRITE (NOUT,*)
      WRITE (NOUT,*) 'Results from full model'
      IF (SVD) THEN
         WRITE (NOUT,*) 'Model not of full rank'
         WRITE (NOUT, *)
      END IF
      WRITE (NOUT,99999) 'Residual sum of squares = ', RSS
```

[NP3390/19/pdf] G02DFF.3

```
WRITE (NOUT,99998) 'Degrees of freedom = ', IDF
         WRITE (NOUT,*)
   80
         READ (NIN,*) INDX
         IF (INDX.NE.O) THEN
            IFAIL = 0
            CALL GO2DFF(IP,Q,NMAX,INDX,RSS,WK,IFAIL)
            IP = IP - 1
            IF (IP.EQ.O) THEN
               WRITE (NOUT,*) 'No terms left in model'
            ELSE
               WRITE (NOUT, 99998) 'Variable', INDX, 'dropped'
               IFAIL = 0
               CALL GO2DDF(N, IP, Q, NMAX, RSS, IDF, B, SE, COV, SVD, IRANK, P, TOL,
                            WK, IFAIL)
               WRITE (NOUT,99999) 'Residual sum of squares = ', RSS
               WRITE (NOUT,99998) 'Degrees of freedom = ', IDF
               WRITE (NOUT,*)
               WRITE (NOUT,*) 'Parameter estimate
                                                     Standard error'
               WRITE (NOUT,*)
               DO 100 J = 1, IP
                  WRITE (NOUT, 99997) B(J), SE(J)
  100
               CONTINUE
               GO TO 80
            END IF
         END IF
      END IF
      STOP
99999 FORMAT (1X, A, e13.4)
99998 FORMAT (1X,A,I4,A)
99997 FORMAT (1X, e15.4, e20.4)
      END
```

9.2 Program Data

```
GO2DFF Example Program Data
12 4 'U' 'M'
1.0 1.4 0.0 0.0 4.32
1.5 2.2 0.0 0.0 5.21
2.0 4.5 0.0 0.0 6.49
2.5 6.1 0.0 0.0 7.10
3.0 7.1 0.0 0.0 7.94
3.5 7.7 0.0 0.0 8.53
4.0 8.3 1.0 4.0 8.84
4.5 8.6 1.0 4.5 9.02
5.0 8.8 1.0 5.0 9.27
5.5 9.0 1.0 5.5 9.43
6.0 9.3 1.0 6.0 9.68
6.5 9.2 1.0 6.5 9.83
2
4
0
```

G02DFF.4 [NP3390/19/pdf]

9.3 Program Results

```
GO2DFF Example Program Results
```

```
Results from full model
Residual sum of squares = 0.8407E-01
Degrees of freedom = 7
```

Variable 2 dropped

Residual sum of squares = 0.2124E+00

Degrees of freedom = 8

Parameter estimate Standard error

```
      0.3637E+01
      0.1508E+00

      0.6126E+00
      0.2801E-01

      -0.6015E+00
      0.4234E+00

      0.1671E+00
      0.7866E-01
```

Variable 4 dropped

Residual sum of squares = 0.3322E+00

Degrees of freedom = 9

Parameter estimate Standard error

[NP3390/19/pdf] G02DFF.5 (last)