#### M01CAF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

# 1 Purpose

M01CAF rearranges a vector of *real* numbers into ascending or descending order.

# 2 Specification

SUBROUTINE MO1CAF(RV, M1, M2, ORDER, IFAIL)

INTEGER M1, M2, IFAIL

real RV(M2) CHARACTER\*1 ORDER

# 3 Description

M01CAF is based on Singleton's implementation of the 'median-of-three' Quicksort algorithm [2], but with two additional modifications. First, small subfiles are sorted by an insertion sort on a separate final pass (Sedgewick [1]). Second, if a subfile is partitioned into two very unbalanced subfiles, the larger of them is flagged for special treatment: before it is partitioned, its end-points are swapped with two random points within it; this makes the worst case behaviour extremely unlikely.

## 4 References

- [1] Sedgewick R (1978) Implementing quicksort programs Comm. ACM 21 847–857
- [2] Singleton R C (1969) An efficient algorithm for sorting with minimal storage: Algorithm 347 Comm. ACM 12 185–187

## 5 Parameters

1:  $RV(M2) - real \operatorname{array}$ 

Input/Output

On entry: elements M1 to M2 of RV must contain real values to be sorted.

On exit: these values are rearranged into sorted order.

**2:** M1 — INTEGER

Input

On entry: the index of the first element of RV to be sorted.

Constraint: M1 > 0.

**3:** M2 — INTEGER

Input

On entry: the index of the last element of RV to be sorted.

Constraint:  $M2 \ge M1$ .

4: ORDER — CHARACTER\*1

Innut

On entry: if ORDER is 'A', the values will be sorted into ascending (i.e., non-decreasing) order; if ORDER is 'D', into descending order.

Constraint: ORDER = 'A' or 'D'.

[NP3390/19/pdf] M01CAF.1

M01 - Sorting

5: IFAIL — INTEGER Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

# 6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors detected by the routine:

```
\begin{split} \text{IFAIL} &= 1 \\ &\quad \text{On entry,} \quad \text{M2} < 1, \\ &\quad \text{or} \quad \text{M1} < 1, \\ &\quad \text{or} \quad \text{M1} > \text{M2}. \end{split} \text{IFAIL} &= 2 \\ &\quad \text{On entry,} \quad \text{ORDER is not 'A' or 'D'.} \end{split}
```

# 7 Accuracy

Not applicable.

#### 8 Further Comments

The average time taken by the routine is approximately proportional to  $n \times \log n$ , where n = M2 - M1 + 1. The worst case time is proportional to  $n^2$  but this is extremely unlikely to occur.

# 9 Example

The example program reads a list of *real* numbers and sorts them into ascending order.

#### 9.1 Program Text

**Note.** The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
MO1CAF Example Program Text
Mark 14 Revised. NAG Copyright 1989.
.. Parameters ..
INTEGER
                 NMAX
PARAMETER
                 (NMAX=100)
INTEGER
                 NIN, NOUT
PARAMETER
                 (NIN=5, NOUT=6)
.. Local Scalars ..
INTEGER
                 I, IFAIL, N
.. Local Arrays ..
real
                 RV(NMAX)
.. External Subroutines ..
EXTERNAL
                 MO1CAF
.. Executable Statements ..
WRITE (NOUT,*) 'MO1CAF Example Program Results'
Skip heading in data file
```

M01CAF.2 [NP3390/19/pdf]

M01 – Sorting

```
READ (NIN,*)
READ (NIN,*)
READ (NIN,*) N

IF (N.GE.1 .AND. N.LE.NMAX) THEN
READ (NIN,*) (RV(I),I=1,N)
IFAIL = 0

*

CALL MO1CAF(RV,1,N,'Ascending',IFAIL)

*

WRITE (NOUT,*)
WRITE (NOUT,*) 'Sorted numbers'
WRITE (NOUT,*)
WRITE (NOUT,*)
WRITE (NOUT,99999) (RV(I),I=1,N)
END IF
STOP

*

99999 FORMAT (1X,10F7.1)
END
```

#### 9.2 Program Data

```
M01CAF Example Program Data
16
1.3 5.9 4.1 2.3 0.5 5.8 1.3 6.5
2.3 0.5 6.5 9.9 2.1 1.1 1.2 8.6
```

#### 9.3 Program Results

MO1CAF Example Program Results

Sorted numbers

```
0.5 0.5 1.1 1.2 1.3 1.3 2.1 2.3 2.3 4.1 5.8 5.9 6.5 6.5 8.6 9.9
```

 $[NP3390/19/pdf] \\ M01CAF.3~(last)$