### C05AXF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

# 1 Purpose

C05AXF attempts to locate a zero of a continuous function using a continuation method based on a secant iteration. It uses reverse communication for evaluating the function.

# 2 Specification

```
SUBROUTINE CO5AXF(X, FX, TOL, IR, SCALE, C, IND, IFAIL)
INTEGER IR, IND, IFAIL

real X, FX, TOL, SCALE, C(26)
```

# 3 Description

This routine uses a modified version of an algorithm given in Swift and Lindfield [1] to compute a zero  $\alpha$  of a continuous function f(x). The algorithm used is based on a continuation method in which a sequence of problems

$$f(x) - \theta_r f(x_0), \quad r = 0, 1, \dots, m$$

are solved, where  $1 = \theta_0 > \theta_1 > \ldots > \theta_m = 0$  (the value of m is determined as the algorithm proceeds) and where  $x_0$  is the user's initial estimate for the zero of f(x). For each  $\theta_r$  the current problem is solved by a robust secant iteration using the solution from earlier problems to compute an initial estimate.

The user must supply an error tolerance TOL. TOL is used directly to control the accuracy of solution of the final problem  $(\theta_m = 0)$  in the continuation method, and  $\sqrt{\text{TOL}}$  is used to control the accuracy in the intermediate problems  $(\theta_1, \theta_2, \dots, \theta_{m-1})$ .

#### 4 References

[1] Swift A and Lindfield G R (1978) Comparison of a continuation method for the numerical solution of a single nonlinear equation *Comput. J.* 21 359–362

### 5 Parameters

*Note:* this routine uses **reverse communication.** Its use involves an initial entry, intermediate exits and re-entries, and a final exit, as indicated by the **parameter IND**. Between intermediate exits and re-entries, all **parameters other than FX must remain unchanged**.

1: X-real Input/Output

On initial entry: an initial approximation to the zero.

On intermediate exit: the point at which f must be evaluated before re-entry to the routine.

On final exit: the final approximation to the zero.

2: FX - real

On initial entry: if IND = 1, FX need not be set. If IND = -1, FX must contain f(X) for the initial value of X.

On intermediate re-entry: FX must contain f(X) for the current value of X.

[NP3390/19/pdf] C05AXF.1

3: TOL-real

On initial entry: a value which controls the accuracy to which the zero is determined. This parameter is used in determining the convergence of the secant iteration used at each stage of the continuation process. It is used directly when solving the last problem ( $\theta_m = 0$  in Section 3), and  $\sqrt{\text{TOL}}$  is used for the problem defined by  $\theta_r$ , r < m. Convergence to the accuracy specified by TOL is not guaranteed, and so the user is recommended to find the zero using at least two values for TOL to check the accuracy obtained.

Constraint: TOL > 0.0.

4: IR — INTEGER

On initial entry: IR indicates the type of error test required, as follows. Solving the problem defined by  $\theta_r$ ,  $1 \le r \le m$ , involves computing a sequence of secant iterates  $x_r^0, x_r^1, \ldots$  This sequence will be considered to have converged only if:

for IR = 0,

$$|x_r^{(i+1)} - x_r^{(i)}| \le \text{EPS} \times \max(1.0, |x_r^{(i)}|),$$

for IR = 1,

$$|x_r^{(i+1)} - x_r^{(i)}| \le \text{EPS},$$

for IR = 2,

$$|x_r^{(i+1)} - x_r^{(i)}| \le \text{EPS} \times |x_r^{(i)}|,$$

for some i > 1; here EPS is either TOL or  $\sqrt{\text{TOL}}$  as discussed above. Note that there are other subsidiary conditions (not given here) which must also be satisfied before the secant iteration is considered to have converged.

Constraint: IR = 0, 1 or 2.

5: SCALE - real Input

On initial entry: a factor for use in determining a significant approximation to the derivative of f(x) at  $x = x_0$ , the initial value. A number of difference approximations to  $f'(x_0)$  are calculated using

$$f'(x_0) \sim (f(x_0 + h) - f(x_0))/h$$

where |h| < |SCALE| and h has the same sign as SCALE. A significance (cancellation) check is made on each difference approximation and the approximation is rejected if insignificant.

Suggested value: the square root of the machine precision.

Constraint: SCALE must be sufficiently large that  $X + SCALE \neq X$  on the computer.

**6:** C(26) — real array Workspace

(C(5) contains the current value,  $\theta_r$ , and C(7) contains a value,  $\lambda_r$ , used in the secant iteration (see Swift and Lindfield [1]); these values may be useful in the event of an error exit.)

7: IND — INTEGER Input/Output

On initial entry: IND must be set to 1 or -1:

if IND = 1, FX need not be set;

if IND = -1, FX must contain f(X).

On intermediate exit: IND contains 2, 3 or 4. The calling program must evaluate f at X, storing the result in FX, and re-enter C05AXF with all other parameters unchanged.

On final exit: IND contains 0.

Constraint: on entry IND = -1, 1, 2, 3 or 4.

C05AXF.2 [NP3390/19/pdf]

8: IFAIL — INTEGER Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

# 6 Error Indicators and Warnings

Errors detected by the routine:

IFAIL = 1

On entry, TOL  $\leq 0.0$ , or IR  $\neq 0$ , 1 or 2.

IFAIL = 2

The parameter IND is incorrectly set on initial or intermediate entry.

IFAIL = 3

SCALE is too small, or significant derivatives of f cannot be computed (this can happen when f is almost constant and non-zero, for any value of SCALE).

IFAIL = 4

The current problem in the continuation sequence cannot be solved, see C(5) for the value of  $\theta_r$ . The most likely explanation is that the current problem has no solution, either because the original problem had no solution or because the continuation path passes through a set of insoluble problems. This latter reason for failure should occur rarely, and not at all if the initial approximation to the zero is sufficiently close. Other possible explanations are that TOL is too small and hence the accuracy requirement is too stringent, or that TOL is too large and the initial approximation too poor, leading to successively worse intermediate solutions.

IFAIL = 5

Continuation away from the initial point is not possible. This error exit will usually occur if the problem has not been properly posed or the error requirement is extremely stringent.

IFAIL = 6

The final problem (with  $\theta_m = 0$ ) cannot be solved. It is likely that too much accuracy has been requested, or that the zero is at  $\alpha = 0$  and IR = 2.

# 7 Accuracy

The accuracy of the approximation to the zero depends on TOL and IR. In general decreasing TOL will give more accurate results. Care must be exercised when using the relative error criterion (IR = 2).

If the zero is at X = 0, or if the initial value of X and the zero bracket the point X = 0, it is likely that an error exit with IFAIL = 4, 5 or 6 will occur.

As discussed in Section 6, it is possible to request too much or too little accuracy. Since it is not possible to achieve more than machine accuracy, a value of  $TOL \ll machine precision$  should not be input and may lead to an error exit with IFAIL = 4, 5 or 6. For the reasons discussed under IFAIL = 4 in Section 6, TOL should not be taken too large, say no larger than TOL = 1.0E-3.

### 8 Further Comments

For most problems, the time taken on each call to C05AXF will be negligible compared with the time spent evaluating f(x) between calls to C05AXF. However, the initial value of X and the choice of TOL will clearly affect the timing. The closer that X is to the root, the less evaluations of f required. The

[NP3390/19/pdf] C05AXF.3

effect of the choice of TOL will not be large, in general, unless TOL is very small, in which case the timing will increase.

If the results obtained from this routine seem unreliable or inaccurate, the user should consider using C05AZF (possibly combined with C05AVF to obtain an interval containing the zero).

One way to check this is to compute the derivative of f at the point X, preferably analytically, or, if this is not possible, numerically, perhaps by using a central difference estimate.

If f'(X) = 0.0, then X must correspond to a multiple zero of f rather than a simple zero.

# 9 Example

To calculate a zero of  $x - e^{-x}$  with initial approximation  $x_0 = 1.0$ , and TOL = 1.0E-3 and 1.0E-4.

### 9.1 Program Text

**Note.** The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
CO5AXF Example Program Text
  Mark 14 Revised. NAG Copyright 1989.
   .. Parameters ..
   INTEGER
                    NOUT
  PARAMETER
                    (NOUT=6)
   .. Local Scalars ..
  real
                    F, SCALE, TOL, X
   INTEGER
                    I, IFAIL, IND, IR
   .. Local Arrays ..
  real
                    C(26)
   .. External Functions ..
  real
                    X02AJF
  EXTERNAL
                    X02AJF
   .. External Subroutines ..
  EXTERNAL
                    CO5AXF
   .. Intrinsic Functions ..
   INTRINSIC
                    EXP, SQRT
   .. Executable Statements ..
   WRITE (NOUT,*) 'CO5AXF Example Program Results'
  SCALE = SQRT(XO2AJF())
   IR = 0
   DO 40 I = 3, 4
      TOL = 10.0e0**(-I)
      WRITE (NOUT,*)
      WRITE (NOUT, 99999) 'TOL = ', TOL
      WRITE (NOUT, *)
      X = 1.0e0
      IFAIL = 1
      IND = 1
20
      CALL CO5AXF(X,F,TOL,IR,SCALE,C,IND,IFAIL)
      IF (IND.NE.O) THEN
         F = X - EXP(-X)
         GO TO 20
      ELSE
         IF (IFAIL.GT.O) THEN
            WRITE (NOUT,99998) 'Error exit, IFAIL =', IFAIL
            IF (IFAIL.EQ.4 .OR. IFAIL.EQ.6) THEN
```

C05AXF.4 [NP3390/19/pdf]

```
WRITE (NOUT,99997) 'Final value = ', X, ' THETA = ',

+ C(5), ' LAMBDA = ', C(7)

END IF

ELSE

WRITE (NOUT,99997) 'Root is ', X

END IF

END IF

40 CONTINUE

STOP

*

99999 FORMAT (1X,A,e10.4)

99998 FORMAT (1X,A,F14.5,A,F10.2,A,F10.2)

END
```

### 9.2 Program Data

None.

### 9.3 Program Results

```
CO5AXF Example Program Results

TOL = 0.1000E-02

Root is 0.56715

TOL = 0.1000E-03

Root is 0.56715
```

[NP3390/19/pdf] C05AXF.5 (last)