

G01ADF – NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

G01ADF calculates the mean, standard deviation and coefficients of skewness and kurtosis for data grouped in a frequency distribution.

2 Specification

```

SUBROUTINE G01ADF(K, X, IFREQ, XMEAN, S2, S3, S4, N, IFAIL)
  INTEGER          K, IFREQ(K), N, IFAIL
  real           X(K), XMEAN, S2, S3, S4

```

3 Description

The input data consist of a univariate frequency distribution, denoted by f_i , for $i = 1, 2, \dots, k-1$, and the boundary values of the classes x_i , for $i = 1, 2, \dots, k$. Thus the frequency associated with the interval (x_i, x_{i+1}) is f_i , and the routine assumes that all the values in this interval are concentrated at the point

$$y_i = (x_{i+1} + x_i)/2, \quad i = 1, 2, \dots, k-1.$$

The following quantities are calculated:

- (a) total frequency,

$$n = \sum_{i=1}^{k-1} f_i.$$

- (b) mean,

$$\bar{y} = \frac{\sum_{i=1}^{k-1} f_i y_i}{n}.$$

- (c) standard deviation,

$$s_2 = \sqrt{\frac{\sum_{i=1}^{k-1} f_i (y_i - \bar{y})^2}{(n-1)}}, \quad n \geq 2.$$

- (d) coefficient of skewness,

$$s_3 = \frac{\sum_{i=1}^{k-1} f_i (y_i - \bar{y})^3}{(n-1) \times s_2^3}, \quad n \geq 2.$$

- (e) coefficient of kurtosis,

$$s_4 = \frac{\sum_{i=1}^{k-1} f_i (y_i - \bar{y})^4}{(n-1) \times s_2^4} - 3, \quad n \geq 2.$$

The routine has been developed primarily for groupings of a continuous variable. If, however, the routine is to be used on the frequency distribution of a discrete variable, taking the values y_1, \dots, y_{k-1} , then the boundary values for the classes may be defined as follows:

- (i) for $k > 2$,
$$\begin{aligned} x_1 &= (3y_1 - y_2)/2 \\ x_j &= (y_{j-1} + y_j)/2, \quad j = 2, \dots, k-1 \\ x_k &= (3y_{k-1} - y_{k-2})/2 \end{aligned}$$
- (ii) for $k = 2$,
$$x_1 = y_1 - a \text{ and } x_2 = y_1 + a \text{ for any } a > 0.$$

4 References

None.

5 Parameters

- 1:** K — INTEGER *Input*
On entry: the number of class boundaries, which is one more than the number of classes of the frequency distribution, k .
Constraint: $K > 1$.
- 2:** X(K) — *real* array *Input*
On entry: the elements of X must contain the boundary values of the classes in ascending order, so that class i is bounded by the values in $X(i)$ and $X(i + 1)$, for $i = 1, 2, \dots, k - 1$.
Constraint: $X(i) < X(i + 1)$, for $i = 1, 2, \dots, k - 1$.
- 3:** IFREQ(K) — INTEGER array *Input*
On entry: the i th element of IFREQ must contain the frequency associated with the i th class, for $i = 1, 2, \dots, k - 1$. IFREQ(k) is not used by the routine.
Constraint: $IFREQ(i) \geq 0$, for $i = 1, 2, \dots, k - 1$ and $\sum_{i=1}^{k-1} IFREQ(i) > 0$.
- 4:** XMEAN — *real* *Output*
On exit: the mean value, \bar{y} .
- 5:** S2 — *real* *Output*
On exit: the standard deviation, s_2 .
- 6:** S3 — *real* *Output*
On exit: the coefficient of skewness, s_3 .
- 7:** S4 — *real* *Output*
On exit: the coefficient of kurtosis, s_4 .
- 8:** N — INTEGER *Output*
On exit: the total frequency, n .
- 9:** IFAIL — INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.
On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

Errors detected by the routine:

IFAIL = 1

On entry, $K \leq 1$.

IFAIL = 2

On entry, the boundary values of the classes in X are not in ascending order.

IFAIL = 3

On entry, $\sum_{i=1}^{k-1} \text{IFREQ}(i) = 0$ or $\text{IFREQ}(i) < 0$ for some i , for $i = 1, 2, \dots, k-1$.

IFAIL = 4

The total frequency, n , is less than 2, hence the quantities s_2 , s_3 and s_4 cannot be calculated.

7 Accuracy

The method used is believed to be stable.

8 Further Comments

The time taken by the routine increases linearly with k .

9 Example

In the example program, NPROB determines the number of sets of data to be analysed. For each analysis, the boundary values of the classes and the frequencies are read. After the routine has been successfully called, the input data and calculated quantities are printed. In the example, there is one set of data, with 14 classes.

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
*      G01ADF Example Program Text
*      Mark 14 Revised.  NAG Copyright 1989.
*      .. Parameters ..
      INTEGER          KMAX
      PARAMETER       (KMAX=50)
      INTEGER          NIN, NOUT
      PARAMETER       (NIN=5,NOUT=6)
*      .. Local Scalars ..
      real            S2, S3, S4, XMEAN
      INTEGER          I, IFAIL, J, K, KMIN1, N, NPROB
*      .. Local Arrays ..
      real            X(KMAX)
      INTEGER          IFREQ(KMAX)
*      .. External Subroutines ..
      EXTERNAL        G01ADF
*      .. Executable Statements ..
      WRITE (NOUT,*) 'G01ADF Example Program Results'
*      Skip heading in data file
      READ (NIN,*)
      READ (NIN,*) NPROB
      DO 20 J = 1, NPROB
         READ (NIN,*) KMIN1
         K = KMIN1 + 1
         IF (K.GE.2 .AND. K.LE.KMAX) THEN
            READ (NIN,*) (X(I),IFREQ(I),I=1,KMIN1), X(K)
            WRITE (NOUT,*)
            WRITE (NOUT,99999) 'Problem ', J
            WRITE (NOUT,99999) 'Number of classes ', KMIN1
            IFAIL = 1
```

```

*
      CALL G01ADF(K,X,IFREQ,XMEAN,S2,S3,S4,N,IFAIL)
*
      WRITE (NOUT,*)
      IF (IFAIL.EQ.0) THEN
        WRITE (NOUT,*) 'Successful call of G01ADF'
        WRITE (NOUT,*)
        WRITE (NOUT,*) '          Class          Frequency'
        WRITE (NOUT,*)
        WRITE (NOUT,99998) (X(I),X(I+1),IFREQ(I),I=1,KMIN1)
        WRITE (NOUT,*)
        WRITE (NOUT,99997) ' Mean ', XMEAN
        WRITE (NOUT,99996) ' Std devn', S2
        WRITE (NOUT,99996) ' Skewness', S3
        WRITE (NOUT,99996) ' Kurtosis', S4
        WRITE (NOUT,99995) ' Number of cases', N
      ELSE
        WRITE (NOUT,99999)
+      'Unsuccessful call of G01ADF. IFAIL = ', IFAIL
      END IF
      ELSE
      STOP
      END IF
20 CONTINUE
      STOP
*
99999 FORMAT (1X,A,I4)
99998 FORMAT (1X,2F10.2,I12)
99997 FORMAT (1X,A,F16.4)
99996 FORMAT (1X,A,F13.4)
99995 FORMAT (1X,A,I8)
      END

```

9.2 Program Data

G01ADF Example Program Data

```

1
14
  9.3      3      12      19      14      52      16      96
  18     121     20     115     22     86     24     70
  26      49     28     31     30     16     32     6
  34       8     36       7    39.7

```

9.3 Program Results

G01ADF Example Program Results

```

Problem      1
Number of classes  14

```

Successful call of G01ADF

Class	Frequency
9.30	3
12.00	19
14.00	52

16.00	18.00	96
18.00	20.00	121
20.00	22.00	115
22.00	24.00	86
24.00	26.00	70
26.00	28.00	49
28.00	30.00	31
30.00	32.00	16
32.00	34.00	6
34.00	36.00	8
36.00	39.70	7
Mean	21.4932	
Std devn	4.9325	
Skewness	0.7072	
Kurtosis	0.5738	
Number of cases	679	
