G01BLF - NAG Fortran Library Routine Document

Note. Before using this routine, please read the Users' Note for your implementation to check the interpretation of bold italicised terms and other implementation-dependent details.

1 Purpose

G01BLF returns the lower tail, upper tail and point probabilities associated with a hypergeometric distribution.

2 Specification

SUBROUTINE GO1BLF(N, L, M, K, PLEK, PGTK, PEQK, IFAIL) INTEGER N, L, M, K, IFAIL real PLEK, PGTK, PEQK

3 Description

Let X denote a random variable having a hypergeometric distribution with parameters n, l and m $(n \ge l \ge 0, n \ge m \ge 0)$. Then

$$\operatorname{Prob}\{X=k\} = \frac{\binom{m}{k} \binom{n-m}{l-k}}{\binom{n}{l}},$$

where $\max(0, l - (n - m)) \le k \le \min(l, m), 0 \le l \le n \text{ and } 0 \le m \le n.$

The hypergeometric distribution may arise if in a population of size n a number m are marked. From this population a sample of size l is drawn and of these k are observed to be marked.

The mean of the distribution $=\frac{lm}{n}$, and the variance $=\frac{lm(n-l)(n-m)}{n^2(n-1)}$.

This routine computes for given n, l, m and k the probabilities:

4 References

[1] Knüsel L (1986) Computation of the chi-square and Poisson distribution SIAM J. Sci. Statist. Comput. 7 1022–1036

5 Parameters

1: N — INTEGER

On entry: the parameter n of the hypergeometric distribution.

Constraint: $N \ge 0$.

2: L — INTEGER

On entry: the parameter l of the hypergeometric distribution.

Constraint: $0 \le L \le N$.

3: M — INTEGER

On entry: the parameter m of the hypergeometric distribution.

Constraint: $0 \le M \le N$.

[NP3390/19/pdf] G01BLF.1

4: K — INTEGER Input

On entry: the integer k which defines the required probabilities.

Constraint: $\max(0, L - (N - M)) \le K \le \min(L, M)$.

5: PLEK-real

On exit: the lower tail probability, $Prob\{X \leq k\}$.

6: PGTK-real

On exit: the upper tail probability, $Prob\{X > k\}$.

7: PEQK-real

On exit: the point probability, $Prob\{X = k\}$.

8: IFAIL — INTEGER Input/Output

On entry: IFAIL must be set to 0, -1 or 1. For users not familiar with this parameter (described in Chapter P01) the recommended value is 0.

On exit: IFAIL = 0 unless the routine detects an error (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors detected by the routine:

IFAIL = 1

On entry, N < 0.

IFAIL = 2

On entry, L < 0, or L > N.

IFAIL = 3

On entry, M < 0, or M > N.

IFAIL = 4

$$\label{eq:constraints} \begin{split} \text{On entry,} \quad & K < 0, \\ & \text{or} \quad & K > L, \\ & \text{or} \quad & K > M, \\ & \text{or} \quad & K < L + M - N. \end{split}$$

IFAIL = 5

On entry, N is too large to be represented exactly as a *real* number.

IFAIL = 6

On entry, the variance (see Section 3) exceeds 10^6 .

7 Accuracy

Results are correct to a relative accuracy of at least 10^{-6} on machines with a precision of 9 or more decimal digits, and to a relative accuracy of at least 10^{-3} on machines of lower precision (provided that the results do not underflow to zero).

G01BLF.2 [NP3390/19/pdf]

8 Further Comments

The time taken by the routine depends on the variance (see Section 3) and on k. For given variance, the time is greatest when $k \approx lm/n$ (= the mean), and is then approximately proportional to the square-root of the variance.

9 Example

This example program reads values of n, l, m and k from a data file until end-of-file is reached, and prints the corresponding probabilities.

9.1 Program Text

Note. The listing of the example program presented below uses bold italicised terms to denote precision-dependent details. Please read the Users' Note for your implementation to check the interpretation of these terms. As explained in the Essential Introduction to this manual, the results produced may not be identical for all implementations.

```
GO1BLF Example Program Text
     Mark 14 Revised. NAG Copyright 1989.
      .. Parameters ..
     INTEGER
                       NIN, NOUT
     PARAMETER
                       (NIN=5, NOUT=6)
      .. Local Scalars ..
     real
                       PEQK, PGTK, PLEK
     INTEGER
                       IFAIL, K, L, M, N
      .. External Subroutines ..
     EXTERNAL
                       G01BLF
      .. Executable Statements ..
     WRITE (NOUT,*) 'GO1BLF Example Program Results'
     Skip heading in data file
     READ (NIN,*)
     WRITE (NOUT,*)
                                                      PGTK
     WRITE (NOUT,*) '
                         N
                                 Μ
                                      K
                                            PLEK
                                                                 PEQK'
                             L
     WRITE (NOUT,*)
  20 READ (NIN, *, END=40) N, L, M, K
      IFAIL = 0
     CALL GO1BLF(N,L,M,K,PLEK,PGTK,PEQK,IFAIL)
     WRITE (NOUT,99999) N, L, M, K, PLEK, PGTK, PEQK
     GO TO 20
  40 STOP
99999 FORMAT (1X,4I4,3F10.5)
     END
```

9.2 Program Data

```
GO1BLF Example Program Data

10 2 5 1 : N, L, M, K

40 10 3 2

155 35 122 22

1000 444 500 220
```

[NP3390/19/pdf] G01BLF.3

9.3 Program Results

GO1BLF Example Program Results

N	L	М	K	PLEK	PGTK	PEQK
10	2	5	1	0.77778	0.22222	0.55556
40	10	3	2	0.98785	0.01215	0.13664
155	35	122	22	0.01101	0.98899	0.00779
1000	444	500	220	0.42429	0.57571	0.04913

G01BLF.4~(last) [NP3390/19/pdf]